

Synchronization between Ipaq and PC with PC2002, below is the detail procedures:

1. Run BT software on both Desktop computer and PDA;
2. Run Microsoft ActiveSync3.5 on desktop;
3. Connect PDA with Desktop by USB connection, so PDA will remember the desktop computer's name;
4. Disconnect the Synchronization connection, on desktop side, please click File→Connection Setting→Allow Serial cable or Infrared connection to this COM port, please remember that the COM port must be **BT LAN host**;
5. To PDA, XTND Monitor→File→Connect to LAN→Fill user name and password;
6. In jump-out menu of Monitor, select the desktop computer name which you want to connect to, then click connect;
7. Start→Programs→ActiveSync;
8. click Sync;
9. Finished, user can see "connection" interface.